

ETSI TS 136 413 V15.8.0 (2020-01)



LTE;
Evolved Universal Terrestrial
Radio Access Network (E-UTRAN);
S1 Application Protocol (S1AP)
(3GPP TS 36.413 version 15.8.0 Release 15)



Reference

RTS/TSGR-0336413vf80

Keywords

LTE

ETSI

650 Route des Lucioles
F-06921 Sophia Antipolis Cedex - FRANCE

Tel.: +33 4 92 94 42 00 Fax: +33 4 93 65 47 16

Siret N° 348 623 562 00017 - NAF 742 C
Association à but non lucratif enregistrée à la
Sous-Préfecture de Grasse (06) N° 7803/88

Important notice

The present document can be downloaded from:

<http://www.etsi.org/standards-search>

The present document may be made available in electronic versions and/or in print. The content of any electronic and/or print versions of the present document shall not be modified without the prior written authorization of ETSI. In case of any existing or perceived difference in contents between such versions and/or in print, the prevailing version of an ETSI deliverable is the one made publicly available in PDF format at www.etsi.org/deliver.

Users of the present document should be aware that the document may be subject to revision or change of status.

Information on the current status of this and other ETSI documents is available at

<https://portal.etsi.org/TB/ETSIDeliverableStatus.aspx>

If you find errors in the present document, please send your comment to one of the following services:

<https://portal.etsi.org/People/CommiteeSupportStaff.aspx>

Copyright Notification

No part may be reproduced or utilized in any form or by any means, electronic or mechanical, including photocopying and microfilm except as authorized by written permission of ETSI.

The content of the PDF version shall not be modified without the written authorization of ETSI.

The copyright and the foregoing restriction extend to reproduction in all media.

© ETSI 2020.

All rights reserved.

DECT™, **PLUGTESTS™**, **UMTS™** and the ETSI logo are trademarks of ETSI registered for the benefit of its Members.

3GPP™ and **LTE™** are trademarks of ETSI registered for the benefit of its Members and of the 3GPP Organizational Partners.

oneM2M™ logo is a trademark of ETSI registered for the benefit of its Members and of the oneM2M Partners.

GSM® and the GSM logo are trademarks registered and owned by the GSM Association.

Intellectual Property Rights

Essential patents

IPRs essential or potentially essential to normative deliverables may have been declared to ETSI. The information pertaining to these essential IPRs, if any, is publicly available for **ETSI members and non-members**, and can be found in ETSI SR 000 314: "*Intellectual Property Rights (IPRs); Essential, or potentially Essential, IPRs notified to ETSI in respect of ETSI standards*", which is available from the ETSI Secretariat. Latest updates are available on the ETSI Web server (<https://ipr.etsi.org/>).

Pursuant to the ETSI IPR Policy, no investigation, including IPR searches, has been carried out by ETSI. No guarantee can be given as to the existence of other IPRs not referenced in ETSI SR 000 314 (or the updates on the ETSI Web server) which are, or may be, or may become, essential to the present document.

Trademarks

The present document may include trademarks and/or tradenames which are asserted and/or registered by their owners. ETSI claims no ownership of these except for any which are indicated as being the property of ETSI, and conveys no right to use or reproduce any trademark and/or tradename. Mention of those trademarks in the present document does not constitute an endorsement by ETSI of products, services or organizations associated with those trademarks.

Legal Notice

This Technical Specification (TS) has been produced by ETSI 3rd Generation Partnership Project (3GPP).

The present document may refer to technical specifications or reports using their 3GPP identities. These shall be interpreted as being references to the corresponding ETSI deliverables.

The cross reference between 3GPP and ETSI identities can be found under <http://webapp.etsi.org/key/queryform.asp>.

Modal verbs terminology

In the present document "**shall**", "**shall not**", "**should**", "**should not**", "**may**", "**need not**", "**will**", "**will not**", "**can**" and "**cannot**" are to be interpreted as described in clause 3.2 of the [ETSI Drafting Rules](#) (Verbal forms for the expression of provisions).

"**must**" and "**must not**" are **NOT** allowed in ETSI deliverables except when used in direct citation.

Contents

Intellectual Property Rights	2
Legal Notice	2
Modal verbs terminology.....	2
Foreword.....	14
1 Scope	15
2 References	15
3 Definitions and abbreviations.....	18
3.1 Definitions	18
3.2 Abbreviations	19
4 General	20
4.1 Procedure Specification Principles.....	20
4.2 Forwards and Backwards Compatibility	21
4.3 Specification Notations	21
5 S1AP Services	22
6 Services Expected from Signalling Transport.....	23
7 Functions of S1AP	24
8 S1AP Procedures	26
8.1 List of S1AP Elementary procedures	26
8.2 E-RAB Management procedures.....	28
8.2.1 E-RAB Setup	28
8.2.1.1 General	28
8.2.1.2 Successful Operation.....	28
8.2.1.3 Unsuccessful Operation	29
8.2.1.4 Abnormal Conditions	30
8.2.2 E-RAB Modify	30
8.2.2.1 General	30
8.2.2.2 Successful Operation.....	30
8.2.2.3 Unsuccessful Operation	31
8.2.2.4 Abnormal Conditions	31
8.2.3 E-RAB Release	32
8.2.3.1 General	32
8.2.3.2 Successful Operation.....	32
8.2.3.2.1 E-RAB Release – MME initiated	32
8.2.3.2.2 E-RAB Release Indication – eNB initiated	33
8.2.3.3 Abnormal Conditions	33
8.2.4 E-RAB Modification Indication	34
8.2.4.1 General	34
8.2.4.2 Successful Operation.....	34
8.2.4.3 Unsuccessful Operation	35
8.2.4.4 Abnormal Conditions	35
8.3 Context Management procedures	35
8.3.1 Initial Context Setup	35
8.3.1.1 General	35
8.3.1.2 Successful Operation.....	35
8.3.1.3 Unsuccessful Operation	39
8.3.1.4 Abnormal Conditions	40
8.3.2 UE Context Release Request (eNB initiated)	40
8.3.2.1 General	40
8.3.2.2 Successful Operation.....	40
8.3.3 UE Context Release (MME initiated).....	41
8.3.3.1 General	41

8.3.3.2	Successful Operation.....	41
8.3.3.3	Abnormal Conditions	42
8.3.4	UE Context Modification.....	42
8.3.4.1	General	42
8.3.4.2	Successful Operation.....	42
8.3.4.3	Unsuccessful Operation	44
8.3.4.4	Abnormal Conditions	44
8.3.5	UE Radio Capability Match.....	44
8.3.5.1	General	44
8.3.5.2	Successful Operation.....	45
8.3.5.3	Unsuccessful Operation	45
8.3.5.4	Abnormal Conditions	45
8.3.6	UE Context Modification Indication	45
8.3.6.1	General	45
8.3.6.2	Successful Operation.....	46
8.3.6.3	Unsuccessful Operation	46
8.3.6.4	Abnormal Conditions	46
8.3.7	UE Context Suspend	46
8.3.7.1	General	46
8.3.7.2	Successful Operation.....	46
8.3.8	UE Context Resume.....	47
8.3.8.1	General	47
8.3.8.2	Successful Operation.....	47
8.3.8.3	Unsuccessful Operation	48
8.3.9	Connection Establishment Indication	48
8.3.9.1	General	48
8.3.9.2	Successful Operation.....	48
8.3.9.3	Unsuccessful Operation	49
8.3.9.4	Abnormal Conditions	49
8.3.10	Retrieve UE Information	49
8.3.10.1	General	49
8.3.10.2	Successful Operation.....	49
8.3.10.3	Unsuccessful Operation	49
8.3.10.4	Abnormal Conditions	49
8.3.11	UE Information Transfer	50
8.3.11.1	General	50
8.3.11.2	Successful Operation.....	50
8.3.11.3	Unsuccessful Operation	50
8.3.11.4	Abnormal Conditions	50
8.3.12	eNB CP Relocation Indication.....	50
8.3.12.1	General	50
8.3.12.2	Successful Operation.....	51
8.3.12.3	Unsuccessful Operation	51
8.3.12.4	Abnormal Conditions	51
8.3.13	MME CP Relocation Indication.....	51
8.3.13.1	General	51
8.3.13.2	Successful Operation.....	51
8.3.13.3	Unsuccessful Operation	52
8.3.13.4	Abnormal Conditions	52
8.4	Handover Signalling.....	52
8.4.1	Handover Preparation	52
8.4.1.1	General	52
8.4.1.2	Successful Operation.....	52
8.4.1.3	Unsuccessful Operation	55
8.4.1.4	Abnormal Conditions	56
8.4.2	Handover Resource Allocation.....	56
8.4.2.1	General	56
8.4.2.2	Successful Operation.....	56
8.4.2.3	Unsuccessful Operation	60
8.4.2.4	Abnormal Conditions	60
8.4.3	Handover Notification	61
8.4.3.1	General	61

8.4.3.2	Successful Operation.....	61
8.4.3.3	Abnormal Conditions	61
8.4.4	Path Switch Request	61
8.4.4.1	General	61
8.4.4.2	Successful Operation.....	61
8.4.4.3	Unsuccessful Operation	64
8.4.4.4	Abnormal Conditions	64
8.4.5	Handover Cancellation	64
8.4.5.1	General	64
8.4.5.2	Successful Operation.....	65
8.4.5.3	Unsuccessful Operation	65
8.4.5.4	Abnormal Conditions	65
8.4.6	eNB Status Transfer.....	65
8.4.6.1	General	65
8.4.6.2	Successful Operation.....	65
8.4.6.3	Unsuccessful Operation	66
8.4.6.4	Abnormal Conditions	66
8.4.7	MME Status Transfer.....	66
8.4.7.1	General	66
8.4.7.2	Successful Operation.....	66
8.4.7.3	Unsuccessful Operation	67
8.4.7.4	Abnormal Conditions	67
8.5	Paging.....	67
8.5.1	General.....	67
8.5.2	Successful Operation	67
8.5.3	Unsuccessful Operation	68
8.5.4	Abnormal Conditions.....	68
8.6	NAS transport.....	68
8.6.1	General.....	68
8.6.2	Successful Operations	69
8.6.2.1	Initial UE Message.....	69
8.6.2.2	DOWNLINK NAS TRANSPORT	70
8.6.2.3	UPLINK NAS TRANSPORT	71
8.6.2.4	NAS NON DELIVERY INDICATION	72
8.6.2.4a	NAS DELIVERY INDICATION	72
8.6.2.5	Reroute NAS Request	73
8.6.3	Unsuccessful Operation	73
8.6.4	Abnormal Conditions.....	73
8.7	Management procedures.....	73
8.7.1	Reset	73
8.7.1.1	General	73
8.7.1.2	Successful Operation.....	74
8.7.1.2.1	Reset Procedure Initiated from the MME.....	74
8.7.1.2.2	Reset Procedure Initiated from the E-UTRAN	75
8.7.1.3	Abnormal Conditions	75
8.7.1.3.1	Abnormal Condition at the EPC	75
8.7.1.3.2	Abnormal Condition at the E-UTRAN	76
8.7.1.3.3	Crossing of Reset Messages	76
8.7.2	Error Indication.....	76
8.7.2.1	General	76
8.7.2.2	Successful Operation.....	76
8.7.2.3	Abnormal Conditions	77
8.7.3	S1 Setup	77
8.7.3.1	General	77
8.7.3.2	Successful Operation.....	77
8.7.3.3	Unsuccessful Operation	78
8.7.3.4	Abnormal Conditions	78
8.7.4	eNB Configuration Update	78
8.7.4.1	General	78
8.7.4.2	Successful Operation.....	78
8.7.4.3	Unsuccessful Operation	79
8.7.4.4	Abnormal Conditions	79

8.7.5	MME Configuration Update	80
8.7.5.1	General	80
8.7.5.2	Successful Operation.....	80
8.7.5.3	Unsuccessful Operation	80
8.7.5.4	Abnormal Conditions	81
8.7.6	Overload Start	81
8.7.6.1	General	81
8.7.6.2	Successful Operation.....	81
8.7.6.3	Unsuccessful Operation	82
8.7.7	Overload Stop	82
8.7.7.1	General	82
8.7.7.2	Successful Operation.....	82
8.7.7.3	Unsuccessful Operation	82
8.8	S1 CDMA2000 Tunnelling Procedures.....	83
8.8.1	General.....	83
8.8.2	Successful Operations.....	83
8.8.2.1	Downlink S1 CDMA2000 Tunnelling	83
8.8.2.2	Uplink S1 CDMA2000 Tunnelling	84
8.8.3	Unsuccessful Operation	84
8.8.4	Abnormal Conditions.....	84
8.9	UE Capability Info Indication	85
8.9.1	General.....	85
8.9.2	Successful Operation	85
8.10	Trace Procedures	85
8.10.1	Trace Start.....	85
8.10.1.1	General	85
8.10.1.2	Successful Operation.....	85
8.10.2	Trace Failure Indication.....	86
8.10.2.1	General	86
8.10.2.2	Successful Operation.....	86
8.10.3	Deactivate Trace	87
8.10.3.1	General	87
8.10.3.2	Successful Operation.....	87
8.10.4	Cell Traffic Trace.....	87
8.10.4.1	General	87
8.10.4.2	Successful Operation.....	87
8.11	Location Reporting Procedures	88
8.11.1	Location Reporting Control	88
8.11.1.1	General	88
8.11.1.2	Successful Operation.....	88
8.11.1.3	Abnormal Conditions	88
8.11.2	Location Report Failure Indication	88
8.11.2.1	General	88
8.11.2.2	Successful Operation.....	89
8.11.3	Location Report	89
8.11.3.1	General	89
8.11.3.2	Successful Operation.....	89
8.11.3.3	Abnormal Conditions	89
8.12	Warning Message Transmission Procedures	89
8.12.1	Write-Replace Warning	89
8.12.1.1	General	89
8.12.1.2	Successful Operation.....	90
8.12.1.3	Abnormal Conditions	91
8.12.2	Kill.....	91
8.12.2.1	General	91
8.12.2.2	Successful Operation.....	91
8.12.3	PWS Restart Indication.....	92
8.12.3.1	General	92
8.12.3.2	Successful Operation.....	92
8.12.4	PWS Failure Indication.....	92
8.12.4.1	General	92
8.12.4.2	Successful Operation.....	92

8.13	eNB Direct Information Transfer	93
8.13.1	General.....	93
8.13.2	Successful Operation	93
8.13.2.1	eNB Direct Information Transfer	93
8.13.3	Abnormal Conditions.....	93
8.14	MME Direct Information Transfer	93
8.14.1	General.....	93
8.14.2	Successful Operation	94
8.14.2.1	MME Direct Information Transfer.....	94
8.14.3	Abnormal Conditions.....	94
8.15	eNB Configuration Transfer.....	94
8.15.1	General.....	94
8.15.2	Successful Operation	94
8.15.2.1	eNB Configuration Transfer.....	94
8.15.3	Abnormal Conditions.....	95
8.16	MME Configuration Transfer.....	95
8.16.1	General.....	95
8.16.2	Successful Operation	95
8.16.2.1	MME Configuration Transfer	95
8.16.3	Abnormal Conditions.....	96
8.17	LPPa transport	96
8.17.1	General.....	96
8.17.2	Successful Operations.....	97
8.17.2.1	DOWNLINK UE ASSOCIATED LPPA TRANSPORT	97
8.17.2.2	UPLINK UE ASSOCIATED LPPA TRANSPORT	97
8.17.2.3	DOWNLINK NON UE ASSOCIATED LPPA TRANSPORT	97
8.17.2.4	UPLINK NON UE ASSOCIATED LPPA TRANSPORT	98
8.17.3	Unsuccessful Operation	98
8.17.4	Abnormal Conditions.....	98
8.18	Secondary RAT Data Usage Report	98
8.18.1	General.....	98
8.18.2	Successful Operations.....	98
8.18.2.1	SECONDARY RAT DATA USAGE REPORT	98
8.18.3	Unsuccessful Operation	99
8.18.4	Abnormal Conditions.....	99
9	Elements for S1AP Communication	100
9.1	Message Functional Definition and Content	100
9.1.1	General.....	100
9.1.2	Message Contents	100
9.1.2.1	Presence	100
9.1.2.2	Criticality	100
9.1.2.3	Range	100
9.1.2.4	Assigned Criticality.....	100
9.1.3	E-RAB Management Messages	101
9.1.3.1	E-RAB SETUP REQUEST.....	101
9.1.3.2	E-RAB SETUP RESPONSE.....	102
9.1.3.3	E-RAB MODIFY REQUEST	103
9.1.3.4	E-RAB MODIFY RESPONSE	104
9.1.3.5	E-RAB RELEASE COMMAND	104
9.1.3.6	E-RAB RELEASE RESPONSE	105
9.1.3.7	E-RAB RELEASE INDICATION.....	105
9.1.3.8	E-RAB MODIFICATION INDICATION	106
9.1.3.9	E-RAB MODIFICATION CONFIRM	107
9.1.4	Context Management Messages	107
9.1.4.1	INITIAL CONTEXT SETUP REQUEST	107
9.1.4.2	Void.....	109
9.1.4.3	INITIAL CONTEXT SETUP RESPONSE	109
9.1.4.4	INITIAL CONTEXT SETUP FAILURE.....	109
9.1.4.5	UE CONTEXT RELEASE REQUEST	110
9.1.4.6	UE CONTEXT RELEASE COMMAND	110
9.1.4.7	UE CONTEXT RELEASE COMPLETE	110

9.1.4.8	UE CONTEXT MODIFICATION REQUEST	111
9.1.4.9	UE CONTEXT MODIFICATION RESPONSE	111
9.1.4.10	UE CONTEXT MODIFICATION FAILURE	111
9.1.4.11	UE RADIO CAPABILITY MATCH REQUEST	112
9.1.4.12	UE RADIO CAPABILITY MATCH RESPONSE	112
9.1.4.13	UE CONTEXT MODIFICATION INDICATION	112
9.1.4.14	UE CONTEXT MODIFICATION CONFIRM	112
9.1.4.15	UE CONTEXT SUSPEND REQUEST	113
9.1.4.16	UE CONTEXT SUSPEND RESPONSE	113
9.1.4.17	UE CONTEXT RESUME REQUEST	113
9.1.4.18	UE CONTEXT RESUME RESPONSE	114
9.1.4.19	UE CONTEXT RESUME FAILURE	114
9.1.4.20	CONNECTION ESTABLISHMENT INDICATION	115
9.1.4.21	RETRIEVE UE INFORMATION	115
9.1.4.22	UE INFORMATION TRANSFER	115
9.1.4.23	eNB CP RELOCATION INDICATION	116
9.1.4.24	MME CP RELOCATION INDICATION	116
9.1.5	Handover Signalling Messages	117
9.1.5.1	HANDOVER REQUIRED	117
9.1.5.2	HANDOVER COMMAND	118
9.1.5.3	HANDOVER PREPARATION FAILURE	119
9.1.5.4	HANDOVER REQUEST	120
9.1.5.5	HANDOVER REQUEST ACKNOWLEDGE	122
9.1.5.6	HANDOVER FAILURE	123
9.1.5.7	HANDOVER NOTIFY	123
9.1.5.8	PATH SWITCH REQUEST	124
9.1.5.9	PATH SWITCH REQUEST ACKNOWLEDGE	125
9.1.5.10	PATH SWITCH REQUEST FAILURE	126
9.1.5.11	HANDOVER CANCEL	126
9.1.5.12	HANDOVER CANCEL ACKNOWLEDGE	126
9.1.5.13	eNB STATUS TRANSFER	126
9.1.5.14	MME STATUS TRANSFER	126
9.1.6	PAGING	127
9.1.7	NAS Transport Messages	128
9.1.7.1	INITIAL UE MESSAGE	128
9.1.7.2	DOWNLINK NAS TRANSPORT	130
9.1.7.3	UPLINK NAS TRANSPORT	130
9.1.7.4	NAS NON DELIVERY INDICATION	131
9.1.7.4a	NAS DELIVERY INDICATION	131
9.1.7.5	REROUTE NAS REQUEST	132
9.1.8	Management messages	132
9.1.8.1	RESET	132
9.1.8.2	RESET ACKNOWLEDGE	132
9.1.8.3	ERROR INDICATION	133
9.1.8.4	S1 SETUP REQUEST	133
9.1.8.5	S1 SETUP RESPONSE	134
9.1.8.6	S1 SETUP FAILURE	135
9.1.8.7	ENB CONFIGURATION UPDATE	135
9.1.8.8	ENB CONFIGURATION UPDATE ACKNOWLEDGE	136
9.1.8.9	ENB CONFIGURATION UPDATE FAILURE	137
9.1.8.10	MME CONFIGURATION UPDATE	137
9.1.8.11	MME CONFIGURATION UPDATE ACKNOWLEDGE	137
9.1.8.12	MME CONFIGURATION UPDATE FAILURE	138
9.1.8.13	OVERLOAD START	138
9.1.8.14	OVERLOAD STOP	138
9.1.9	S1 CDMA2000 Tunnelling Messages	139
9.1.9.1	DOWNLINK S1 CDMA2000 TUNNELLING	139
9.1.9.2	UPLINK S1 CDMA2000 TUNNELLING	139
9.1.10	UE CAPABILITY INFO INDICATION	139
9.1.11	Trace Messages	140
9.1.11.1	TRACE START	140
9.1.11.2	TRACE FAILURE INDICATION	140

9.1.11.3	DEACTIVATE TRACE	141
9.1.12	Location Reporting Messages.....	141
9.1.12.1	LOCATION REPORTING CONTROL	141
9.1.12.2	LOCATION REPORT FAILURE INDICATION	141
9.1.12.3	LOCATION REPORT	141
9.1.13	Warning Message Transmission Messages.....	142
9.1.13.1	WRITE-REPLACE WARNING REQUEST	142
9.1.13.2	WRITE-REPLACE WARNING RESPONSE	142
9.1.13.3	KILL REQUEST.....	142
9.1.13.4	KILL RESPONSE.....	143
9.1.13.5	PWS RESTART INDICATION	143
9.1.13.6	PWS FAILURE INDICATION	144
9.1.14	eNB DIRECT INFORMATION TRANSFER	144
9.1.15	MME DIRECT INFORMATION TRANSFER	144
9.1.16	eNB CONFIGURATION TRANSFER.....	144
9.1.17	MME CONFIGURATION TRANSFER.....	144
9.1.18	CELL TRAFFIC TRACE.....	145
9.1.19	LPPa Transport Messages.....	145
9.1.19.1	DOWNLINK UE ASSOCIATED LPPA TRANSPORT.....	145
9.1.19.2	UPLINK UE ASSOCIATED LPPA TRANSPORT	145
9.1.19.3	DOWNLINK NON UE ASSOCIATED LPPA TRANSPORT	146
9.1.19.4	UPLINK NON UE ASSOCIATED LPPA TRANSPORT.....	146
9.1.20	Secondary RAT Report Data Usage Messages.....	146
9.1.20.1	SECONDARY RAT DATA USAGE REPORT.....	146
9.2	Information Element Definitions.....	147
9.2.0	General.....	147
9.2.1	Radio Network Layer Related IEs	147
9.2.1.1	Message Type	147
9.2.1.2	E-RAB ID	147
9.2.1.3	Cause.....	147
9.2.1.3a	RRC Establishment Cause	151
9.2.1.4	Trace Activation.....	151
9.2.1.5	Source ID	152
9.2.1.6	Target ID.....	152
9.2.1.7	Source eNB to Target eNB Transparent Container	153
9.2.1.8	Target eNB to Source eNB Transparent Container	154
9.2.1.9	Source RNC to Target RNC Transparent Container	155
9.2.1.10	Target RNC to Source RNC Transparent Container	155
9.2.1.11	Source BSS to Target BSS Transparent Container	155
9.2.1.12	Target BSS to Source BSS Transparent Container	155
9.2.1.13	Handover Type.....	155
9.2.1.14	Extended RNC-ID.....	155
9.2.1.15	E-RAB Level QoS Parameters.....	155
9.2.1.16	Paging DRX	156
9.2.1.17	Paging Cause.....	156
9.2.1.18	GBR QoS Information	156
9.2.1.19	Bit Rate	157
9.2.1.20	UE Aggregate Maximum Bit Rate	158
9.2.1.21	Criticality Diagnostics.....	158
9.2.1.22	Handover Restriction List	159
9.2.1.23	CDMA2000-PDU	161
9.2.1.24	CDMA2000 RAT Type.....	161
9.2.1.25	CDMA2000 Sector ID	162
9.2.1.26	Security Context.....	162
9.2.1.27	UE Radio Capability	162
9.2.1.28	CDMA2000 HO Status	162
9.2.1.29	CDMA2000 HO Required Indication	163
9.2.1.30	1xRTT MEID.....	163
9.2.1.31	eNB Status Transfer Transparent Container.....	163
9.2.1.32	COUNT Value	165
9.2.1.33	CDMA2000 1xRTT RAND	165
9.2.1.34	Request Type.....	165

9.2.1.35	CDMA2000 1xRTT SRVCC Info.....	166
9.2.1.36	E-RAB List	166
9.2.1.37	Global eNB ID	167
9.2.1.37a	Global en-gNB ID.....	167
9.2.1.38	E-UTRAN CGI	167
9.2.1.39	Subscriber Profile ID for RAT/Frequency priority	167
9.2.1.40	UE Security Capabilities	168
9.2.1.41	Security Key.....	168
9.2.1.42	UE History Information	168
9.2.1.43	Last Visited Cell Information.....	169
9.2.1.43a	Last Visited E-UTRAN Cell Information	169
9.2.1.43b	Last Visited GERAN Cell Information	169
9.2.1.44	Message Identifier.....	170
9.2.1.45	Serial Number	170
9.2.1.46	Warning Area List.....	170
9.2.1.47	Emergency Area ID.....	170
9.2.1.48	Repetition Period.....	171
9.2.1.49	Number of Broadcasts Requested	171
9.2.1.50	Warning Type	171
9.2.1.51	Warning Security Information	171
9.2.1.52	Data Coding Scheme	171
9.2.1.53	Warning Message Contents.....	172
9.2.1.54	Broadcast Completed Area List	172
9.2.1.55	Inter-system Information Transfer Type	172
9.2.1.56	Source To Target Transparent Container	173
9.2.1.57	Target To Source Transparent Container	173
9.2.1.58	SRVCC Operation Possible	174
9.2.1.59	SRVCC HO Indication.....	174
9.2.1.60	Allocation and Retention Priority	174
9.2.1.61	Time to wait	175
9.2.1.62	CSG Id	175
9.2.1.63	CSG Id List	175
9.2.1.64	MS Classmark 2	176
9.2.1.65	MS Classmark 3	176
9.2.1.66	Cell Type.....	176
9.2.1.67	Old BSS to New BSS Information	176
9.2.1.68	Layer 3 Information	176
9.2.1.69	E-UTRAN Round Trip Delay Estimation Info	176
9.2.1.70	Broadcast Cancelled Area List.....	176
9.2.1.71	Number of Broadcasts.....	177
9.2.1.72	Concurrent Warning Message Indicator.....	177
9.2.1.73	CSG Membership Status	178
9.2.1.74	Cell Access Mode	178
9.2.1.75	Extended Repetition Period.....	178
9.2.1.76	Data Forwarding Not Possible	178
9.2.1.77	PS Service Not Available.....	178
9.2.1.78	Paging Priority	178
9.2.1.79	Relay Node Indicator	179
9.2.1.80	Correlation ID	179
9.2.1.81	MDT Configuration	179
9.2.1.82	MME Relay Support Indicator.....	182
9.2.1.83	Management Based MDT Allowed.....	182
9.2.1.84	GW Context Release Indication.....	183
9.2.1.85	Voice Support Match Indicator	183
9.2.1.86	M3 Configuration.....	183
9.2.1.87	M4 Configuration.....	183
9.2.1.88	M5 Configuration.....	183
9.2.1.89	MDT PLMN List	184
9.2.1.90	COUNT Value Extended	184
9.2.1.91	Kill-all Warning Messages Indicator	184
9.2.1.92	LHN ID	184
9.2.1.93	User Location Information	184

9.2.1.94	MBSFN-ResultToLog.....	185
9.2.1.95	EARFCN.....	185
9.2.1.96	Expected UE Behaviour.....	185
9.2.1.97	Expected UE Activity Behaviour.....	186
9.2.1.98	UE Radio Capability for Paging.....	186
9.2.1.99	ProSe Authorized.....	186
9.2.1.100	COUNT Value for PDCP SN Length 18.....	187
9.2.1.101	M6 Configuration.....	187
9.2.1.102	M7 Configuration.....	187
9.2.1.103	Assistance Data for Paging.....	188
9.2.1.104	Assistance Data for Recommended Cells.....	188
9.2.1.105	Information on Recommended Cells and eNBs for Paging.....	188
9.2.1.106	Recommended Cells for Paging.....	188
9.2.1.107	Recommended eNBs for Paging.....	189
9.2.1.108	Assistance Data for CE capable UEs.....	189
9.2.1.109	Cell Identifier and Coverage Enhancement Level.....	190
9.2.1.110	Paging Attempt Information.....	190
9.2.1.111	Paging eDRX Information.....	190
9.2.1.112	UE Retention Information.....	190
9.2.1.113	UE User Plane CIoT Support Indicator.....	190
9.2.1.114	NB-IoT Default Paging DRX.....	191
9.2.1.115	NB-IoT Paging eDRX Information.....	191
9.2.1.116	Bearer Type.....	191
9.2.1.117	RAT Type.....	191
9.2.1.118	CE-mode-B Support Indicator.....	191
9.2.1.119	SRVCC Operation Not Possible.....	191
9.2.1.120	V2X Services Authorized.....	192
9.2.1.121	Served DCNs Items.....	192
9.2.1.122	UE Sidelink Aggregate Maximum Bit Rate.....	192
9.2.1.123	Enhanced Coverage Restricted.....	192
9.2.1.124	Secondary RAT Usage Report List.....	193
9.2.1.125	Handover Flag.....	194
9.2.1.126	Extended Bit Rate.....	194
9.2.1.127	NR UE Security Capabilities.....	194
9.2.1.128	UE Application layer measurement configuration.....	194
9.2.1.129	CE-mode-B Restricted.....	195
9.2.1.130	Packet Loss Rate.....	196
9.2.1.131	Global RAN Node ID.....	196
9.2.1.132	Global gNB ID.....	196
9.2.1.133	Source NG-RAN Node To Target NG-RAN Node Transparent Container.....	196
9.2.1.134	Target NG-RAN Node To Source NG-RAN Node Transparent Container.....	197
9.2.1.135	LTE-M Indication.....	197
9.2.1.136	Aerial UE subscription information.....	197
9.2.1.137	Bluetooth Measurement Configuration.....	197
9.2.1.138	WLAN Measurement Configuration.....	197
9.2.1.139	Warning Area Coordinates.....	198
9.2.1.140	Subscription Based UE Differentiation Information.....	198
9.2.1.141	PSCell Information.....	199
9.2.1.142	NR CGI.....	200
9.2.1.143	Time Since Secondary Node Release.....	200
9.2.2	Transport Network Layer Related IEs.....	201
9.2.2.1	Transport Layer Address.....	201
9.2.2.2	GTP-TEID.....	201
9.2.2.3	Tunnel Information.....	201
9.2.3	NAS Related IEs.....	201
9.2.3.1	LAI.....	201
9.2.3.2	RAC.....	201
9.2.3.3	MME UE S1AP ID.....	202
9.2.3.4	eNB UE S1AP ID.....	202
9.2.3.5	NAS-PDU.....	202
9.2.3.6	S-TMSI.....	202
9.2.3.7	TAC.....	202

9.2.3.8	PLMN Identity	202
9.2.3.9	GUMMEI	203
9.2.3.10	UE Identity Index value	203
9.2.3.11	IMSI	203
9.2.3.12	MMEC	203
9.2.3.13	UE Paging Identity	204
9.2.3.14	DL Forwarding	204
9.2.3.15	Direct Forwarding Path Availability	204
9.2.3.16	TAI	204
9.2.3.17	Relative MME Capacity	205
9.2.3.18	UE S1AP ID pair	205
9.2.3.19	Overload Response	205
9.2.3.20	Overload Action	205
9.2.3.21	CS Fallback Indicator	205
9.2.3.22	CN Domain	206
9.2.3.23	RIM Transfer	206
9.2.3.24	RIM Information	206
9.2.3.25	RIM Routing Address	206
9.2.3.26	SON Configuration Transfer	207
9.2.3.26a	EN-DC SON Configuration Transfer	208
9.2.3.27	SON Information	208
9.2.3.28	SON Information Reply	209
9.2.3.29	X2 TNL Configuration Info	209
9.2.3.30	NAS Security Parameters from E-UTRAN	210
9.2.3.31	NAS Security Parameters to E-UTRAN	210
9.2.3.32	LPPa-PDU	211
9.2.3.33	Routing ID	211
9.2.3.34	Time Synchronisation Info	211
9.2.3.35	Void	211
9.2.3.36	Traffic Load Reduction Indication	211
9.2.3.37	Additional CS Fallback Indicator	212
9.2.3.38	Masked IMEISV	212
9.2.3.39	SON Information Report	212
9.2.3.40	RLF Report Information	212
9.2.3.41	Muting Pattern Information	212
9.2.3.42	Synchronisation Information	213
9.2.3.43	Listening Subframe Pattern	213
9.2.3.44	MME Group ID	213
9.2.3.45	Additional GUTI	214
9.2.3.46	Extended UE Identity Index Value	214
9.2.3.47	NB-IoT UE Identity Index Value	214
9.2.3.48	DL NAS PDU Delivey Request	214
9.2.3.49	DL CP Security Information	214
9.2.3.50	UL CP Security Information	214
9.2.3.51	UE Capability Info Request	215
9.2.3.52	5GS TAI	215
9.2.3.53	5GS TAC	215
9.2.3.54	End Indication	215
9.2.3.55	Pending Data Indication	215
9.3	Message and Information Element Abstract Syntax (with ASN.1)	216
9.3.0	General	216
9.3.1	Usage of private message mechanism for non-standard use	216
9.3.2	Elementary Procedure Definitions	217
9.3.3	PDU Definitions	231
9.3.4	Information Element Definitions	290
9.3.5	Common Definitions	343
9.3.6	Constant Definitions	343
9.3.7	Container Definitions	352
9.4	Message Transfer Syntax	356
9.5	Timers	356
10	Handling of Unknown, Unforeseen and Erroneous Protocol Data	357